

Instrukcja instalacji niepodpisanych cyfrowo sterowników w systemie Windows 8


System Windows 8 wprowadził nowe ostrzejsze zasady instalacji sterowników urządzeń. Dlatego też mimo iż urządzenie jest poprawnie wpięte do komputera i wybrane do zainstalowania sterowniki poprawne – system wyświetli komunikat, jak by nie odnalazł sterowników do tego urządzenia.

Aby wymusić instalację należy wyłączyć wymuszanie podpisu sterowników w systemie.

- Będąc w trybie „Modern UI” najjeżdżamy na prawy dolny róg ekranu, aż pojawi się menu i wybieramy **Settings / Ustawienia**:



- Następnie **Change PC settings / Zmień ustawienia komputera**:



- Zaznaczamy **General / Ogólne** i z dołu listy wybieramy **Advanced start-up / Uruchamianie zaawansowane** i klikamy przycisk **Restart now / Uruchom ponownie**

The image shows a screenshot of the Windows Settings application. On the left is a navigation pane titled 'PC settings' with several categories: Notifications, Search, Share, General (highlighted in blue), Privacy, Devices, Ease of Access, Sync your settings, HomeGroup, and Windows Update. The main content area on the right shows the 'Advanced start-up' section, which is currently selected. Above it are sections for 'Language preferences', 'Available storage' (showing 206 GB available), and 'Refresh your PC without affecting your files'. The 'Advanced start-up' section includes a description and a 'Restart now' button. A vertical scrollbar is visible on the right edge of the settings window.

PC settings

- Notifications
- Search
- Share
- General**
- Privacy
- Devices
- Ease of Access
- Sync your settings
- HomeGroup
- Windows Update

Language preferences

Available storage

You have 206 GB available. See how much space your apps are using.

[View app sizes](#)

Refresh your PC without affecting your files

If your PC isn't running well, you can refresh it without losing your photos, music, videos and other personal files.

[Get started](#)

Remove everything and reinstall Windows

If you want to recycle your PC or completely start again, you can reset it to its factory settings.


[Get started](#)

Advanced start-up


Start up from a device or disc (such as a USB drive or DVD), change Windows start-up settings or restore Windows from a system image. This will restart your PC.

[Restart now](#)


- Komputer uruchomi się ponownie z ekranem na którym wybieramy **Troubleshoot / Rozwiąż problemy**




- Następnie wybieramy opcję **Advanced / Opcje zaawansowane**:



- **Ustawienia uruchamiania / Startup settings:**



- Następnie klikamy **Uruchom ponownie / Restart**



- Po ponownym uruchomieniu naciskamy na klawiaturze **F7** - **Wyłącz wymuszanie podpisu sterowników / Disable driver signature enforcement**

Startup Settings

Press a number to choose from the options below:

Use number keys or functions keys F1-F9.

- 1) Enable debugging
- 2) Enable boot logging
- 3) Enable low-resolution video
- 4) Enable Safe Mode
- 5) Enable Safe Mode with Networking
- 6) Enable Safe Mode with Command Prompt
- 7) Disable driver signature enforcement
- 8) Disable early launch anti-malware protection
- 9) Disable automatic restart after failure

Press F10 for more options

Press Enter to return to your operating system

Teraz po ponownym uruchomieniu komputer podczas instalacji zapyta czy chcemy instalować niepodpisany sterownik.